



AGUACEROWX USER GUIDE

Observations and hydrology

Surface stations, storm reports, river gauges and precipitation analyses draw on the same map as models and radar. Station overlays come from the toolbar. Gridded analyses come from the sidebar.

-
- | | |
|----------------------------|----------------------------|
| 01 ASOS and METARs | 02 Local storm reports |
| 03 River and stream gauges | 04 RTMA |
| 05 Stage IV precipitation | 06 Flash flood guidance |
| 07 National Water Model | 08 Sea surface temperature |

BEFORE YOU START

- The **Surface obs**, **LSR** and **Stream gauges** toolbar buttons work the same way: single-click opens the settings, double-click turns the overlay on or off.
- RTMA, Stage IV and sea surface temperature are data types in the sidebar. Open **Select Data**, then click the data type above the bundle list.
- To add one field to the map you already have, open **Edit Layers** and click **Add Layer**.
- The National Water Model is in the model picker, and flash flood guidance is in the **NOAA data** menu.


01 ASOS and METARs

Surface station plots with raw METARs, wet bulb and relative humidity, RAWS stations and your own colormaps.


- 1 Single-click **Surface obs** on the toolbar.
- 2 Turn on **Enable Surface Obs**.
- 3 Under **Networks**, pick **Both**, **ASOS** or **RAWS**.
- 4 Under **Display Mode**, keep **Station Plots** or pick one variable, such as **Wet Bulb** or **Relative Humidity**.
- 5 For a single variable, click **Load Colormap** to color the stations with your own colormap.
- 6 Hover a station for its latest readings. Click it for an **ASOS Meteogram** of about the last 24 hours.

TIPS

- Turn on **Raw METAR** under **Popup fields** to show the raw report when you hover a station.
- Raise **Station Spacing** to thin out crowded stations when you zoom out.
- Double-click **Surface obs** to turn the stations on or off without opening the settings.



The Surface obs button and its settings.



ASOS station plots across the United States.


02 Local storm reports

Hail, wind, tornado, flood and snow reports from the NWS, plus CoCoRaHS rain gauges.


- 1 Single-click **LSR** on the toolbar.
- 2 Turn on **Show Reports**.
- 3 Pick a **Time window**, from **15 minutes** to **All reports**.
- 4 Under **Report categories**, turn categories on or off. Turn on **CoCoRaHS 24h precip** to add the gauges.
- 5 Pick a **Marker style** and set the **Marker density**.
- 6 Click a report on the map for its magnitude, location and remarks.

TIPS

- The **Current reports** tab lists every report. Search it, then click a report to fly to it.
- Turn on **Update reports with time** to show each report only once the time slider reaches it.



The LSR button and the Local storm reports menu.



Hail and wind reports over MRMS reflectivity in Texas.

The **Custom** marker style, which uses your own icons, needs Professional.


03 River and stream gauges

NWPS river and tide gauges colored by flood category. Click one for its observed and forecast hydrograph.

- 1 Single-click **Stream gauges** on the toolbar.
- 2 Turn on **Enable stream gauges**.
- 3 Under **Time**, choose **Current observations**, or **Follow slider** to color gauges by the stage at the slider time, including the forecast.
- 4 Under **Flood categories**, turn off the categories you want to hide.
- 5 Click a gauge to open its hydrograph.

TIPS

- Scroll to zoom the hydrograph and drag to pan. Click **Reset** to zoom back out.
- Right-click the hydrograph to copy or download it.




Stream gauges with an observed and forecast hydrograph.

04 RTMA

Real-Time Mesoscale Analysis surface fields, such as temperature, dew point, wind gusts and fire weather indices.

- 1 Open the sidebar on **Select Data**.
- 2 Click **RTMA** in the data type filter.
- 3 Click a bundle in the list to load it.
- 4 To add one field instead, open **Edit Layers**, click **Add Layer**, then **RTMA**, and pick a product such as **2m Temperature**.




RTMA 2 m temperature with county values.

Every RTMA product is on every plan. Free loops 1 hour of RTMA, and longer loops need a paid plan.

05 Stage IV precipitation

NCEP multisensor precipitation at about 4.8 km, with totals from 1 hour to a week.

- 1 Open the sidebar on **Select Data**.
- 2 Click **Stage IV** in the data type filter.
- 3 Click a bundle in the list to load it.
- 4 To change the total, open **Edit Layers**, click the layer's field name and pick another, such as **24 Hour Precipitation** or **1 Week Precipitation**.



The Stage IV data type in the sidebar.


06 Flash flood guidance

River Forecast Center guidance: how much rain it takes to cause flash flooding, for 1, 3 and 6 hours across CONUS and 12 hours in the Mid-Atlantic.

- 1 Click **NOAA data** on the toolbar to open **Forecast Products**.
- 2 Click the **RFC** tab.
- 3 Under **Flash Flood Guidance**, turn on **1 Hour**, **3 Hour**, **6 Hour** or **12 Hour**.
- 4 Click the map to read the guidance at a point.

TIPS

- The **Outlooks** data type in the sidebar has the same picker. A product picked there replaces the layers on the panel.



One-hour flash flood guidance across the United States.

07 National Water Model ENTHUSIAST

Short-, medium- and long-range streamflow, soil, snow and runoff for 2.7 million river reaches.

- 1 In the sidebar, click the model menu, which shows the current model's name, to open the model picker.
- 2 Type **NWM** in **Search models....**
- 3 Pick **NWM Short Range**, **NWM Medium Range** or **NWM Long Range**.
- 4 Open **Edit Layers**, click **Add Layer**, then **Model** and **Hydrology**.
- 5 Pick a field, such as **Streamflow**, **Snow Water Equivalent** or **Top-Layer Soil Saturation**.

Short range is an 18-hour hourly forecast. Medium-range streamflow is hourly out to 10 days, and long-range streamflow is every 6 hours out to 30 days. The NWM models are not in the Free model list.

08 Sea surface temperature

Sea surface temperature, its anomaly and change, and tropical cyclone heat potential from three ocean analyses.

- 1 Open the sidebar on **Select Data**.
- 2 Click **SSTs** in the data type filter.
- 3 Pick a source: **CRW** (NOAA Coral Reef Watch), **CDAS** or **ARMOR3D**.
- 4 Click a bundle in the list to load it.
- 5 To add one field instead, use **Add Layer**, then **SSTs**, and pick a product such as **7-Day SST Change** or **Tropical Cyclone Heat Potential**.

TIPS

- Draw a cross section over an SST layer to slice the ocean below the surface. See the Soundings guide.